

# **GDataSystems - Version 0.1 (BETA)**

# **Server Setup**

A standard VPS server will be suitable to host the database, web server, and shiny server. Here are the instructions to setup the server on a UBUNTU operating system.

Configuring the GDataSystems server.

### **Installing PosgreSQL14**

sudo apt install postgresql postgresql-client

#### Checking install

systemctl status postgresql.service

# Replacing postgres user password (Optional)

sudo -u postgres psql
postgres=# \password postgres
postgres=# \q

#### **Installing postgis 3**

sudo sudo apt install gnupg2 sudo apt install postgis postgresql-14-postgis-3

#### <u>Listening to all addresses</u> -Remember to open port 5432

sudo nano /etc/postgresql/14/main/postgresql.conf listen\_addresses = '\*'

# <u>Set Client authentication (adjust properly, below is an example to a very permissive configuration).</u>

sudo nano /etc/postgresql/14/main/pg\_hba.conf # TYPE DATABASE USER ADDRESS METHOD host all all 127.0.0.1/32 md5

# Restarting PostgreSQL

systemctl restart postgresql.service

## Installing Apache2 and R

sudo apt install apache2 sudo apt install r-base sudo apt-get install libpq-dev sudo apt-get install gdal-bin proj-bin libgdal-dev libproj-dev

#### Installing the necessary R packages

sudo R install.packages('DT') install.packages('rpostgis') install.packages('rgdal') install.packages('leaflet')

### **GDataSystems – System Implementation Tutorial**



install.packages('leaflet.extras')
install.packages('glue')
install.packages('gpplot2')
install.packages('shiny')
install.packages('shinymanager')
install.packages('dplyr')
install.packages('rmarkdown')
q()

#### **Installing shiny**

sudo apt-get install gdebi-core wget https://download3.rstudio.org/ubuntu-18.04/x86\_64/shiny-server-1.5.20.1002-amd64.deb sudo gdebi shiny-server-1.5.20.1002-amd64.deb

#### Configuring shiny as a server

sudo a2enmod proxy sudo a2enmod proxy\_http sudo a2enmod proxy\_wstunnel nano /etc/apache2/sites-enabled/000-default.conf

#### Add the following to the file at the end.

## Add the following lines to the file /etc/shiny-server/shiny-server.conf

disable\_websockets true; sanitize\_errors off;disable\_protocols xdr-streaming xhr-streaming iframe-eventsource iframehtmlfile;

# **Installing PHP**

sudo apt -y install software-properties-common sudo add-apt-repository ppa:ondrej/php sudo apt-get update sudo apt -y install php7.4 sudo apt-get install php7.4-pgsql sudo apt install php7.4-mbstring

That's it! The server is now configured and ready to receive the mineral exploration database.